

# **Rich Media Environment Technical Specification**

Candidate Version 1.0 – 14 Oct 2008

**Open Mobile Alliance** OMA-TS-RME-V1\_0-20081014-C

Use of this document is subject to all of the terms and conditions of the Use Agreement located at http://www.openmobilealliance.org/UseAgreement.html.

Unless this document is clearly designated as an approved specification, this document is a work in process, is not an approved Open Mobile Alliance<sup>TM</sup> specification, and is subject to revision or removal without notice.

You may use this document or any part of the document for internal or educational purposes only, provided you do not modify, edit or take out of context the information in this document in any manner. Information contained in this document may be used, at your sole risk, for any purposes. You may not use this document in any other manner without the prior written permission of the Open Mobile Alliance. The Open Mobile Alliance authorizes you to copy this document, provided that you retain all copyright and other proprietary notices contained in the original materials on any copies of the materials and that you comply strictly with these terms. This copyright permission does not constitute an endorsement of the products or services. The Open Mobile Alliance assumes no responsibility for errors or omissions in this document.

Each Open Mobile Alliance member has agreed to use reasonable endeavors to inform the Open Mobile Alliance in a timely manner of Essential IPR as it becomes aware that the Essential IPR is related to the prepared or published specification. However, the members do not have an obligation to conduct IPR searches. The declared Essential IPR is publicly available to members and non-members of the Open Mobile Alliance and may be found on the "OMA IPR Declarations" list at <a href="http://www.openmobilealliance.org/ipr.html">http://www.openmobilealliance.org/ipr.html</a>. The Open Mobile Alliance has not conducted an independent IPR review of this document and the information contained herein, and makes no representations or warranties regarding third party IPR, including without limitation patents, copyrights or trade secret rights. This document may contain inventions for which you must obtain licenses from third parties before making, using or selling the inventions. Defined terms above are set forth in the schedule to the Open Mobile Alliance Application Form.

NO REPRESENTATIONS OR WARRANTIES (WHETHER EXPRESS OR IMPLIED) ARE MADE BY THE OPEN MOBILE ALLIANCE OR ANY OPEN MOBILE ALLIANCE MEMBER OR ITS AFFILIATES REGARDING ANY OF THE IPR'S REPRESENTED ON THE "OMA IPR DECLARATIONS" LIST, INCLUDING, BUT NOT LIMITED TO THE ACCURACY, COMPLETENESS, VALIDITY OR RELEVANCE OF THE INFORMATION OR WHETHER OR NOT SUCH RIGHTS ARE ESSENTIAL OR NON-ESSENTIAL.

THE OPEN MOBILE ALLIANCE IS NOT LIABLE FOR AND HEREBY DISCLAIMS ANY DIRECT, INDIRECT, PUNITIVE, SPECIAL, INCIDENTAL, CONSEQUENTIAL, OR EXEMPLARY DAMAGES ARISING OUT OF OR IN CONNECTION WITH THE USE OF DOCUMENTS AND THE INFORMATION CONTAINED IN THE DOCUMENTS.

© 2008 Open Mobile Alliance Ltd. All Rights Reserved. Used with the permission of the Open Mobile Alliance Ltd. under the terms set forth above.

# **Contents**

1.	SCOPE	5
2.	REFERENCES	6
	2.1 NORMATIVE REFERENCES	
	2.2 Informative References	
	TERMINOLOGY AND CONVENTIONS	
	3.1 CONVENTIONS	
	3.2 DEFINITIONS	
3	3.3 ABBREVIATIONS	
4.	INTRODUCTION	10
5.	NAMESPACE DEFINITION	11
6.	SCENE DESCRIPTION	12
6	6.1 SVG TINY 1.2	12
6	6.2 Scene Description Extensions	12
6	6.3 URI SUPPORT	12
7.	SCENE COMMANDS	13
	7.1 UPDATE COMMANDS	
	7.1 OPDATE COMMANDS	
-	7.3 ACTIVATION COMMANDS	
	7.4 SCRIPT AS A COMMAND	
	7.5 SEEKING IN THE RME TIMELINE	
	7.6 SCENE COMMAND DOCUMENT	
8.		
8	8.1 SCRIPTING LANGUAGE	14
	8.2 SCRIPT PROCESSING	
	8.3 UDOM API	
8	8.4 EXTENSIONS TO UDOM API	
8	8.5 ESMP BINDINGS TO UDOM	14
9.	EVENTS	15
	9.1 LIST OF SUPPORTED EVENTS	
	9.2 RME DEFINED EVENTS	
	9.2.1 Screen Orientation event	
	9.2.2 Key Identifiers	
9	9.3 EVENT PROCESSING MODEL	
10.		
1	10.1 TIMING MODEL	
	10.2 PROCESSING MODEL	
11.		
	11.1 RME DOCUMENT	
1	11.1.1 Specific data signaling	
1	11.2 3GP FILE.	
_	11.3 MULTIPART MIME	
•	11.3.1 Multipart MIME RELATED	
	11.3.2 Multipart MIME MIXED	
1	11.4 STREAMS OF RME UNITS	
-	11.4.1 Random Access Point	
1	11.5 STORAGE OF RME DATA LOCALLY	
	11.6 OTHER DELIVERY CONTEXTS	
12.		
	12.1 STATIC CAPABILITIES	
1.	THE CHARLIES AND	,

12.2	2 DYNAMIC CAPABILITIES	22
13.	HOST SERVICES	23
13.1	1 FONT	23
13.2		
13.3	3 IMAGE	23
13.4	4 AUDIO	23
13.5	5 CONTENT SECURITY AND PROTECTION	23
APPE	NDIX A. CHANGE HISTORY (INFORMATIVE)	24
<b>A.1</b>		
<b>A.2</b>	DRAFT/CANDIDATE VERSION 1.0 HISTORY	24
APPE	ENDIX B. STATIC CONFORMANCE REQUIREMENTS (NORMATIVE)	25
<b>B.1</b>	S CIT I SK IEVIE CELEVI	
APPE	NDIX C. FONT USAGE FOR CONTENT AUTHORING GUIDELINES (INFORMATIVE)	26
APPE	NDIX D. DEFINITION OF ECMA SCRIPT BINDINGS FOR UDOM EXTENSIONS	27
APPE	NDIX E. UAPROF VOCABULARY DEFINITIONS	28
<b>E.1</b>	RME CAPABLE	28
<b>E.2</b>		
<b>E.3</b>	RME DELIVERY CONTEXTS	28
<b>E.4</b>	SCREEN ORIENTATIONS	29
E.5	SCREENDEFAULTORIENTATION	29
<b>E.6</b>	CURRENT SCREEN ORIENTATION	30
E.7	CURRENTRMESCREENSIZE	30
Tak	oles	
Table	1 DIMS unit header data and how it is retrieved for RME data in RME documents	18

# 1. Scope

The Scope of this document is to specify all the components, interfaces and functionalities needed by the Rich-Media Environment Enabler, according to the [RME\_RD] and the [RME\_AD] documents.

A joint work has been agreed to define the RME enabler with the 3GPP SA4 working group. As a consequence the RME TS is based on the 3GPP SA4 Dynamic and Interactive Multimedia Scene [DIMS]

The objectives of this document, detailed below, are:

- To complement [DIMS] in OMA specific areas
- To ensure compliancy and compatibility with [DIMS]
- To fulfill RME Requirements not taken in account by [DIMS]
- To ensure RME will remain bearer agnostic and usable outside of 3GPP networks

#### Specific OMA areas

In addition to the RME requirements not fulfilled by [DIMS] or fulfilled in a 3GPP specific manner, the RME specification needs to complement [DIMS] in areas owned by OMA such as:

- Specific functions (e.g. Soft key mapping, event handling and fonts)
- Overall Processing Model
- UAProf vocabulary
- Integration with other OMA enablers
- Alignment with related mark-up languages (e.g. XHTML).

#### **Compliance with DIMS**

A coordination process has been pursued with the 3GPP SA4 working group since the delivery of the OMA RD document. The intent between the BT-MAE and 3GPP SA4 is to develop a common Core Rich-Media specification usable on any bearer, but well adapted to 3GPP networks. In order to avoid market fragmentation, the RME TS will reference the [DIMS] specification in sections related to the core common rich-media specification and will specify additional features when needed for the OMA environment. The RME TS is defined as a superset of [DIMS].

DIMS and RME share the same MIME type definition: video/richmedia+xml for stream-based RTP transport of rich media data.

#### RME requirements not taken in account by DIMS

When developing DIMS, the 3GPP SA4 working group has delivered the document [DIMS REQ] which adapted the RME requirements to DIMS needs. In particular Annex A of [DIMS REQ] lists all the RME requirements not taken in account for the [DIMS] specification development. The RME specification should define the complementary text for these requirements.

#### Usage of RME outside of 3GPP networks/environment

The RME requirement document states that the RME enabler is agnostic of any bearers, networks, OSs, etc. [DIMS] is not totally agnostic of "any" bearers outside of 3GPP networks and environment.

RME intends to maximize the usage of common technologies across various environments where possible.

The RME specification needs to provide equivalent functionalities to [DIMS] for non 3GPP environment, e.g.: 3GPP2, DVB, OMA-PUSH.

#### 2. References

#### 2.1 Normative References

[BCAST] "Mobile Broadcast Services", Version 1.0 – 7 August 2008, OMA-TS-BCAST Services-V1 0-20080807-

C, URL: <a href="http://www.openmobilealliance.org/">http://www.openmobilealliance.org/</a>

[DCD] "Enabler Release Definition for DCD", Version 1.0 – 23 June 2008, OMA-ERELD-DCD-V1 0-

20080623-D, URL: http://www.openmobilealliance.org/

[DIMS] "Dynamic Interactive Multimedia Scenes (DIMS)", version 7.1.0, 3GPP specification,

URL: http://www.3gpp.org/ftp/Specs/html-info/26142.htm

[DOM3\_EVENT] "Document Object Model (DOM) Level 3 Events Specification", World Wide Web Consortium, Working

Draft, 21 December 2007, URL: http://www.w3.org/TR/DOM-Level-3-Events

[ESMP] "ECMAScript Mobile Profile", Version 1.1, Open Mobile Alliance™,

OMA-TS-ESMP-V1 1, URL: http://www.openmobilealliance.org/

[LASER] ISO/IEC 14496-20:2006 Information technology — Coding of audio-visual objects — Part 20:

Lightweight Application Scene Representation (LASeR) and Simple Aggregation Format (SAF), including

ISO/IEC 14496-20:2006/COR1, ISO/IEC 14496-20:2006/AMD1

[MAXE] "Media Access Events", World Wide Web Consortium Working Draft, 13 October 2006,

URL: http://www.w3.org/TR/MediaAccessEvents/

[OFF] ISO/IEC 14496-22 Information technology — Coding of audio-visual objects — Part 22: Open Font

Format

[PUSH] "Enabler Release Definition for Push", Version 2.2, Open Mobile Alliance<sup>TM</sup>, OMA-ERELD-Push-V2\_2-

200710002-C, URL: http://www.openmobilealliance.org/

[RFC2046] "Multipurpose Internet Mail Extensions (MIME) Part Two: Media Types" N. Freed and N. Borenstein,

November 1996, URL: <a href="http://www.ietf.org/rfc/rfc2046.txt">http://www.ietf.org/rfc/rfc2046.txt</a>

[RFC2119] "Key words for use in RFCs to Indicate Requirement Levels", S. Bradner, March 1997,

URL: http://www.ietf.org/rfc/rfc2119.txt

[RFC2387] "The MIME Multipart/Related Content-type", E. Levinson, August 1998,

URL: http://www.ietf.org/rfc/rfc2387.txt

[RME\_AD] "Rich Media Environment Architecture", Open Mobile Alliance<sup>TM</sup> OMA-AD-Rich\_Media\_Environment-

V1\_0,

URL: http://www.openmobilealliance.org/ftp/Public documents/BT/MAE/Permanent documents/OMA-

AD-RME-V1\_0\_0-20070615-D.zip

[RME\_RD] "Rich Media Environment Requirements", Open Mobile Alliance™, OMA-RD Rich-Media-

Environment-V1\_0,

URL:

http://member.openmobilealliance.org/ftp/Public documents/BT/MAE/Permanent documents/OMA-RD-

Rich-Media-Environment-V1 0-20050923-C.zip

[SCRRULES] "SCR Rules and Procedures", Open Mobile Alliance™, OMA-ORG-SCR Rules and Procedures,

URL: http://www.openmobilealliance.org/

[SMIL] "Synchronized Multimedia Integration Language (SMIL 2.1)", World Wide Web Consortium,

Recommendation, URL: http://www.w3.org/TR/2005/REC-SMIL2-20051213/

[SVG] "Scalable Vector Graphics (SVG) Tiny 1.2 Specification", World Wide Web Consortium

Recommendation, URL: <a href="http://www.w3.org/TR/SVGMobile12/">http://www.w3.org/TR/SVGMobile12/</a>

[UAPROF] "User Agent Profile", , Version 2.0, Open Mobile Alliance™, OMA-TS-UAProf-V2\_0

URL: http://www.openmobilealliance.org/

[URISCH] "URI Schemes for the Mobile Applications Environment", Version 1.0, Open Mobile Alliance™, OMA-

TS-URI\_schemes\_V1\_0 URL: www.openmobilealliance.org/

# 2.2 Informative References

[DIMS REQ]

"DIMS Technical requirements", 3GPP document S4-050800, URL: <a href="http://www.3gpp.org/ftp/tsg\_sa/WG4\_CODEC/TSGS4\_37/Docs/S4-050800.zip">http://www.3gpp.org/ftp/tsg\_sa/WG4\_CODEC/TSGS4\_37/Docs/S4-050800.zip</a>

# 3. Terminology and Conventions

#### 3.1 Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in [RFC2119].

All sections and appendixes, except "Scope" and "Introduction", are normative, unless they are explicitly indicated to be informative.

#### 3.2 Definitions

Normal Play Time The normal play time at a particular instant in a stream is equal to the time it takes to play the stream, at

normal pace and without interrupts, from the start of the stream to the particular instant.

RME data XML data consisting of either initial scene data or scene commands.

**RME timeline** Timeline graded by the normal play time of an RME stream.

RME Unit The smallest process-able unit of RME data. For streaming delivery the RME Unit is equivalent to DIMS Unit

as defined in Section 5.6 [DIMS]. For HTTP delivering the RME Unit equals the body of the DIMS unit.

**Rich media** Media consisting of aggregation of a number of different media types such as vector graphics, still images,

video and audio.

Scene The description of temporal and spatial layout of objects (included or by references) such as vector graphics,

images, audios and their linkage to each other

**Scene Commands** Information defining modifications to a scene.

## 3.3 Abbreviations

**3GPP** Third Generation Partnership Program

AAC Advanced Audio Coding
AD Architecture Document

API Application Programmer's Interface

BCAST OMA Mobile Broadcast Services Enabler Suite

**DCD** Dynamic Content Delivery enabler

**DIMS** Dynamic and Interactive Multimedia Scenes

**DOM** Document Object Model

DRAP Dynamic Random Access Point
DRM Digital Rights Management
DVB Digital Video Broadcasting

**ECMA** European Computer Manufacturers Association

ESMP ECMA Script Mobile Profile
HTML Hypertext Markup Language
HTTP Hypertext Transfer Protocol

MBMS Multimedia Broadcast Multicast Service

OMA Open Mobile Alliance

RD Requirement Document

RME Rich Media Environment
RTP Real-time Transport Protocol

RU RME Unit

SDP Session Description Protocol
 SVG Scalable Vector Graphics
 TS Technical Specification

**uDOM** Micro DOM

URL Uniform Resource Locator

XHTML Extensible HyperText Markup Language

XML Extensible Markup Language

#### 4. Introduction

The rich media environment (RME) specification defines a language for describing rich media content, which can be distributed to and displayed on mobile devices. RME content consists of scenes of visual objects, such as video, images, animation and text, and audio objects that are composed together to give the user a richer experience. The system contains means to continuously update the scene with new information replacing only the parts that are changing. It will thus be possible to keep part of the scene while updating other parts of the scene, thereby saving both communication bandwidth and device processing power. It is however, also possible to replace the current scene with a new scene, if desired.

Typical applications for RME are mobile TV Clients, dynamic application user interfaces, multi-player gaming, and on-device portals.

The RME system consists of the RME Client and the RME server. The RME Client typically resides on the mobile terminal and provides the capability to display RME data, handle dynamic updates to the RME Scene as well as local and remote interaction with the scene objects. Typically the server is the source of data and provides RME data to the client.

# 5. Namespace definition

The RME specification is an extension of the DIMS specification defined in [DIMS]. All XML entities defined in DIMS are in the namespace "http://www.3gpp.org/richmedia/". The current specification defines additional XML entities.

Although the development of the two specifications has been done in close cooperation, a new namespace is defined here to avoid the risk of name clashing, and in addition, to serve as a placeholder for functional entities defined in this document. XML entities defined in the current document are defined in the namespace "http://www.openmobilealliance.org/richmedia".

# 6. Scene Description

This section defines the XML language constructs that are used to describe an RME scene. The scene description defines visual and audio objects and the layout of these objects on the drawing canvas. The description of a scene also defines any temporal relation between the objects in the scene, as well as local and remote interaction with scene objects.

## 6.1 SVG Tiny 1.2

The scene description language is based on the SVG Tiny 1.2 specification [SVG]. The RME scene description language SHALL support all language features that are included in the SVG feature string <a href="http://www.w3.org/Graphics/SVG/feature/1.2/#SVG-all">http://www.w3.org/Graphics/SVG/feature/1.2/#SVG-all</a>.

## **6.2 Scene Description Extensions**

The scene description language in addition to the SVG Tiny 1.2 as defined in Section 6.1, SHALL support the extensions defined in Section 5.4.2 in [DIMS]. These extensions comply with SVG Tiny 1.2 Extension Conformance Requirements in Section D.6 in [SVG].

## 6.3 URI support

The RME enabler SHOULD support URI schemes according to [URISCH].

#### 7. Scene Commands

This section defines XML language constructs used to accomplish changes to an RME scene. The commands can be synchronized to the time line of the scene.

## 7.1 Update Commands

The update commands are used to modify an RME scene. The update commands allow insert, delete, replace and add operations on the RME scene. The syntax and semantics of the update commands are defined in Section 5.5.1 in [DIMS] and SHALL be supported by the RME enabler. The update commands are based on the MPEG4 part 20 specification [LASER].

## 7.2 State Management Commands

The RME enabler provides state management capabilities through the save/restore/clean commands, which operate on DOM attributes. The mechanisms are specified in Section 5.5.2, in [DIMS] and SHALL be supported by the RME enabler.

The state management mechanisms can be a potential security risk. The security measures defined in 5.5.2 of [DIMS] SHALL be used.

An RME enabler implementation may impose additional security mechanisms.

#### 7.3 Activation Commands

The RME system SHALL support the activate/deactivate commands as specified in Section 5.5.3 in [DIMS]. These commands operate on the nodes of the DOM tree and provide means to temporarily activate/deactivate a branch of the DOM tree.

## 7.4 Script as a Command

Scripts can be sent to the client for immediate execution. Scripts SHALL have access to the RME Scene, including the ability to modify the DOM. The RME Client SHALL NOT load these scripts in the DOM. The command for sending such scripts is defined in Section 5.5.5 in [DIMS] and SHALL be supported by the RME enabler.

## 7.5 Seeking in the RME timeline

To perform relative seek backward and forward in the RME timeline, the seek command as defined in Section 5.5.6 in [DIMS] SHALL be supported by the RME enabler for locally stored data (for e.g. RME content packaged in a 3gp file). The device is NOT REQUIRED to buffer any data from a data stream. The RME enabler MAY support this command for streamed data.

#### 7.6 Scene Command document

The <sceneCommandGroup> element defines a wrapper element for scene commands. The <sceneCommandGroup> element is defined in the RME namespace and has no attributes. By wrapping scene commands in this element a valid XML document is created.

Download requests for <sceneCommandGroup> documents can be made from the scene using the <updates> element as defined in Section 5.4.2.6 in [DIMS] or scripts. The commands within a <sceneCommandGroup> SHALL be applied in the order they appear in the element.

The retrieved commands do not have any media time and SHALL be applied according to the begin time of the <updates> element for update requests and as soon as they arrive for script requests.

## 8. Scripting functionality

This section defines the scripting capabilities available in the RME enabler. The RME enabler SHALL include support for script execution. Scripts are loaded to the client either as part of the initial scene (see Section 5), as an update (see Section 7.1) or in an immediate script execution unit (see Section 7.4).

Scripts used in RME context may pose security risks. RME does not define any security mechanisms of its own for script execution and relies on the protection mechanisms provided by the underlying scripting environments. The authors and implementations are recommended to exercise caution when scripts are used in the context of RME.

## 8.1 Scripting language

The RME Client SHALL support the ECMA Script Mobile Profile as defined in [ESMP] and MAY support other scripting languages.

## 8.2 Script processing

The scripts supplied with the initial scene or in scene updates are loaded into the DOM of the scene and SHALL be executed according to the rules in Section in 15.2.1 (SVG Script Processing) in [SVG].

Scripts sent from the server to the client according to Section 7.4 SHALL be executed according to Section 10.1in the present specification. These scripts SHALL NOT be loaded into the DOM and SHALL be removed as soon as they have finished their execution.

#### 8.3 uDOM API

The RME system SHALL allow scripts to access the RME Scene using the uDOM API as defined in appendix A in [SVG].

#### 8.4 Extensions to uDOM API

The RME system SHALL in addition to the uDOM API defined in Section 8.3 support the APIs necessary for scene extensions as defined in Section 6.3 in [DIMS].

## 8.5 ESMP bindings to uDOM

The uDOM used in RME SHALL bind to the ECMA script mobile profile using the bindings defined in Appendix O in [SVG]. The extensions to the uDOM defined in this specification SHALL be bound to ECMA script mobile profile using the bindings defined in Appendix D in the present specification.

#### 9. Events

The RME enabler supports event creation, dispatching and handling on the client. An RME Client SHALL handle events according to the DOM-Level-3 Events specification as specified in Section 13 in [SVG].

## 9.1 List of Supported Events

The RME Client SHALL support creation and dispatching of the following events:

- All events of SVG Tiny 1.2 as defined in Section 13.2 in [SVG]
- The Media Access Events as defined in [MAXE]
- Events defined in the DIMS specification Section 6.1 in [DIMS]
- Events defined in Section 9.2 in the present specification

The Event object property "type" SHALL map to "Event identifier", as defined by SVG, for all events defined outside of the SVG specification.

#### 9.2 RME defined events

#### 9.2.1 Screen Orientation event

The RME enabler SHALL support the screen orientation events as defined in Section 5.4.2.8 in [DIMS]. The RME enabler SHALL support the ScreenOrientationEvent interface as defined below. This interface is a superset and redefinition of the interface with the same name defined in Section 6.1.3 in [DIMS]. The superset is a result of the softKeysLocation attribute not present in DIMS.

This interface provides contextual information associated with change in Screen Orientation modes. Supported event types are ScreenOrientationPortrait and ScreenOrientationLandscape.

```
interface ScreenOrientationEvent : Event
{
   readonly attribute unsigned long screenWidth;
   readonly attribute unsigned long screenHeight;
   readonly attribute unsigned long screenAngle;
   readonly attribute DOMString softKeysLocation;
}
```

#### Attributes

#### 9.2.2 Key Identifiers

The RME enabler SHALL, in addition to the key identifiers defined in [DOM3\_EVENT] support the following key identifiers in the KeyboardEvent interface:

"Softkey\_1" – The primary softkey.

"Softkey 2" - The secondary softkey.

"Softkey\_3" - Optional softkey.

"Softkey n" – Additional optional softkeys 4 and beyond where n indicates the number.

"Joystick Left" - Indicates 'left' movement by the rocker/9-way switch.

"Joystick Right" – Indicates 'right' movement by the rocker/9-way switch.

"Joystick\_Up" - Indicates 'up' movement by the rocker/9-way switch.

"Joystick Down" - Indicates 'down' movement by the rocker/9-way switch.

"Joystick\_Center" – Indicates 'center' movement by the rocker/9-way switch.

"Joystick\_UpLeft" - Indicates 'up/left' movement by the rocker/9-way switch

"Joystick UpRight" - Indicates 'up/right' movement by the rocker/9-way switch

"Joystick DownLeft" - Indicates 'down/left' movement by the rocker/9-way switch

"Joystick DownRight" - Indicates 'down/right' movement by the rocker/9-way switch

## 9.3 Event Processing Model

The processing of events SHALL follow the DOM-Level-3 Events specification as used in Section 13 in [SVG].

The RME enabler MAY support the capture phase completion of the DOM Events flow.

Event processing SHOULD be considered an atomic action. After an event has been created and dispatched, the processing of the event SHOULD continue until completion. For further information see Section 1.2.2.5 in [DOM3\_EVENT].

## 10. Timing Model and Processing Model

In this section the overall processing and timing model is defined. This is the relation between processing and timing of the RME scene objects: Scripts, events, updates and the regular scene objects. The intrinsic timing and processing details of the objects themselves is discussed in their respective section.

## 10.1 Timing model

The RME enabler processes the following objects: Initial scenes, scene commands, events, scripts and rendering. All processing objects SHALL be processed at their normal play time. Objects of different types but with the same play time can be processed in implementation specific order. Objects of the same type and with the same normal play time can be handled in any order.

Objects in the RME scene can be synchronized relative to each other. The synchronization requires that timing information is available for all elements that are to be synchronized. Obtaining timing information for the media elements is dependent on the particular format used for the underlying media of these elements.

Scene commands can be synchronized to the RME Scene time. The command structure does not contain timing information and relies on the transport layer timing information. The correlation between the transport layer timing and the normal play time is handled by the transport layer.

The definition of transport layer time in different delivery contexts is defined in Section 11 below.

## 10.2 Processing Model

The processing model for handling the RME units is defined in Section 5.8 in [DIMS].

The playback algorithm of a compliant RME Engine SHALL produce the same result as the algorithm described below with the following high-level steps for each execution cycle:

- 1. Load the initial RME scene and initialize the scene time:
- 2. Compute the new scene time t (begin of execution cycle);
- 3. Decode any RU with a scene time below or equal to *t*, and not yet presented in earlier execution cycles, as well as any RU with no specified time;
- 4. Execute commands from RUs decoded at step 3;
- 5. Event resolution and media synchronization
  - 5.1. Process all events according to the DOM event model [DOM3\_EVENT] and resolve all begin and end times that can be resolved according to the SMIL Timing Model, in clause 10 of [SMIL];
  - 5.2. Determine active media objects by inspecting begin and end times,
  - 5.3. If there are more events generated, go to 5.1
- 6. For each active media object, calculate its normal play time, and prepare for rendering of next frame.
- 7. Render the audio and visual element of the scene tree according to the SVG rendering model as described in Clause 3 of [SVG] (end of execution cycle).

## 11. Packaging and delivery

The RME data can be packaged, accessed and delivered through the following mechanisms:

- RME document
- 3gp file
- Multipart MIME
- Streamed sequences of RME Units
- Local storage

The primary addressed delivery context in this specification is 3GPP networks. Additional delivery contexts can be added in future releases. Some delivery contexts e.g. broadcast streaming context, require the client to perform tune-in.

This section also defines how the media time for updates is obtained in different delivery contexts.

#### 11.1 RME document

An RME document SHALL consist of either a scene (see Section 6) or scene commands packaged in a <sceneCommandGroup> element as defined in Section 7.6in the current specification. The document SHALL constitute a valid XML document.

The MIME type for Initial scenes SHALL be "application/richmedia+xml".

The MIME type for <sceneCommandGroup> documents SHALL be "application/richmediacommand+xml".

An RME documents containing a scene command groups is recommended to be stored with the file extension "scg" as a matter of best practice. <sup>1</sup>

It SHALL be possible to deliver the RME document using point to point (e.g.: HTTP), or broadcast/multicast (FLUTE) mechanisms.

## 11.1.1 Specific data signaling

RME data transported as documents does not contain the DIMS Unit header part. The table below indicates how the information in the DIMS unit header is retrieved when the RME data is transported as RME documents.

Field	Signaling in DIMS (RTP/3GP)	Signaling in RME (HTTP)
S	Indicates if the body is a scene or not	Signaled in the HTTP Content-Type (MIME) field (see Section 11.1)
M	Indicates if the body is a random access point	Not of interest in error free transport without tune-in
I	Signals redundant body	
D	Signals exit of multi unit random access point	
P	Signal if the unit is essential or not	
С	Signals if the body is compressed	Signaled in the HTTP Content-Encoding field

Table 1 DIMS unit header data and how it is retrieved for RME data in RME documents.

The security variables *useFullRequestHost* and *pathComponents* are in [DIMS] only defined for streamed delivery of data. For RME data delivered as RME documents the security variables *useFullRequestHost* and *pathComponents* shall be set as

© 2008 Open Mobile Alliance Ltd. All Rights Reserved.

Used with the permission of the Open Mobile Alliance Ltd. under the terms as stated in this document.

<sup>&</sup>lt;sup>1</sup> The mime type should be review if we decide to use the OMA process or to do an IETF registration.

*name=value* pairs as extensions to the MIME type in the Content-Type identification of the document. The usage of these parameters SHALL be supported as defined in Section 5.5.2 in [DIMS].

Example Usage:

Content-Type = application/richmedia+xml;useFullRequestHost=1;pathComponents=4

## 11.2 3gp file

The RME enablers SHALL support packaging of RME data into 3GP files according to Section 7.2 in [DIMS]

The 3GP file format supports progressive download. In this case the media time for the updates SHALL be the sample times in the 3GP file.

## 11.3 Multipart MIME

#### 11.3.1 Multipart MIME RELATED

The RME enabler SHOULD support multipart MIME delivery of the type RELATED [RFC2387]. Multipart RELATED is a transport packaging mechanism allowing related MIME messages e.g. initial scene and updates to the scene, to be transmitted in one request.

Example usage of Multipart MIME:

```
------Multipart Message - Begin------
Content-type: multipart/related; boundary="RME"
--RME
Content-type: application/richmedia+xml
<svg>
     <text>This is your initial scene</text>
</svg>
--RME
Content-type: application/richmediacommands+xml
<sceneCommandGroup>
     <insert>....</insert>
      <add>...... </add>
      <delete>.....</delete>
      <doScript>.....</doScript>
</sceneCommandGroup>
--RME--
 ------Multipart Message - End------
```

#### 11.3.2 Multipart MIME MIXED

The RME enabler SHOULD support multipart MIME delivery of the type MIXED [RFC2046]. Multipart MIXED is a transport packaging mechanism allowing unrelated MIME messages e.g. updates, to be transmitted in one request.

#### 11.4 Streams of RME units

A packet of streamable RME data SHALL consist of an RU defined as the DU in Section 5.6 in [DIMS]. The RME enabler SHALL support RTP delivery of RUs using the payload format and SDP parameters defined in Section 7.3 in [DIMS].

The streaming distribution can be of the type one-to-one (e.g.: PSS) and one-to-many (e.g.: BCAST).

The MIME type for streaming over RTP SHALL be "video/richmedia+xml".

In this case, the media time for updates SHALL be the RTP time stamps.

#### 11.4.1 Random Access Point

Random access points are used to perform tune-in, random access and error recovery in a RTP streaming environment. The RME enabler SHALL support the Random Access Mechanism as defined in Section 5.9 in [DIMS] including support for Dynamic Random Access Points DRAP specified in Section 5.5.4 in [DIMS].

## 11.5 Storage of RME data locally

The RME Client SHALL support retrieving 3GP files and RME data including RME documents from the local file system of the device.

## 11.6 Other delivery contexts

Besides the delivery mechanism defined in Section 11.1 and 11.4.1 other delivery contexts can provide desirable functionality for an RME service. RME does not preclude any delivery contexts that usefully provide the client with RME data. Particularly the OMA-BCAST [BCAST] enabler, the OMA-PUSH [PUSH] enabler and the OMA-DCD [DCD] enabler MAY be used.

# 12. Capabilities, Configuration and Management

## 12.1 Static Capabilities

Static device capabilities for RME are advertised using the facilities provided by OMA UAProf [UAPROF]. The following UAProf vocabulary is defined, and SHOULD be supported by device profiles describing RME capable devices:

Attribute	Component	Description	Resolution	Datatype	Example
RMECapable	SoftwarePlatform	Indicates whether the device provides Rich Media User Agent Services.	Locked	Boolean	Yes, No
RMEVersion	SoftwarePlatform	Defines version of the Rich Media Enabler (RME) capability within the device.	Locked	Literal	"1.0"
RichMediaDeliveryContext	SoftwarePlatform	List of RME Delivery contexts the device supports for transporting RME data streams. Property value is a list of supported contexts,	Append	Literal, Bag	"HTTP", "RTP", "FLUTE
		where each item in the list is a context name.			
RichMediaPackagingFormat s	SoftwarePlatform	List of packaging formats the device supports for	Append	Literal,	"3GP", "multipar
		packaging Rich Media data streams. Property value is a list of supported formats, where each item in the list is a packaging format name.		Bag	t", "MULTI PART"
SupportedScreenOrientation s	SoftwarePlatform	Describes the list of supported screen orientation capabilities.	Append	Integer, Bag	0,90,180, 270
		Default "landscape" is defined as 0 degrees.			
		Default "portrait" is defined as 90 degrees.			
		References:			
		3GPP 26.142 v7.1.0 Section 5.4.2.8 OMA RME TS Section 9.2.1 MPEG 20			
ScreenDefaultOrientation	SoftwarePlatform	Describes the default orientation of a device as either 0 (landscape ) or 90 (portrait).	Locked	Integer	90

# 12.2 Dynamic Capabilities

Dynamic capabilities are currently available via ECMAScript API interface (see Section 9.2.1). When dynamic capabilities reporting is implemented in the networked environment, remote access to this vocabulary MAY be provided.

The following vocabulary is defined, but, because of its dynamic nature need only be supported through the specified ECMAScript API:

Attribute	Component	Description	Resolution	Datat ype	Example
ScreenOrientatio n	TBD DCAP	Shows the current screen orientation. "portrait" is always long dimension vertical. "landscape" is always long dimension horizontal. An angular reference assumes "landscape" is 0 or 180 degrees and "portrait" is 90 or 270 degrees. (definition matches with ScreenOrientations)	Dynamic	Integ er	0,90,180,270
RichMediaScreen Height	TBD DCAP	Contains the current running screen viewport height for a DIMS/RME application in pixels. Height is relative to CurrentScreenOrientation as the origin is always located at the top-left corner of the screen.	Dynamic	Integ er	500
RichMediaScreen Width	TBD DCAP	Contains the current running screen viewport width for a DIMS/RME application in pixels. Width is relative to CurrentScreenOrientation as the origin is always located at the top-left corner of the screen.	Dynamic	Integ er	300

#### 13. Host Services

#### 13.1 Font

RME Client implementations SHALL support downloadable OpenType fonts [OFF] with TrueType outlines. TrueType hinting SHALL be supported for improved text readability, and advanced typographic features MAY be supported.

SVG font support is included as part of the SVG specification.

See Appendix C for guidelines on font usage.

Downloadable OpenType fonts SHALL be identified in the RME content using 'font-face-src' and 'font-face-uri' elements from [SVG].

#### 13.2 Video

The video formats that are made available by the client device SHALL be accessible by the RME Client.

#### **13.3 Image**

The image formats that are made available by the client device SHALL be accessible by the RME Client.

#### 13.4 Audio

The audio formats that are made available by the client device SHALL be accessible by the RME Client.

Note: In the ETR the required codecs will be specified on a per delivery context basis (e.g.: H263 and AAC+ for MBMS)

#### 13.5 Content security and protection

The RME enabler does not define a particular content protection or security mechanism. The RME enabler MAY use the OMA DRM enabler to provide content protection. The usage of OMA DRM is implementation dependent.

# Appendix A. Change History

# (Informative)

# A.1 Approved Version History

Reference	<b>Date Description</b>	
n/a n/a		No prior version -or- No previous version within OMA

# A.2 Draft/Candidate Version 1.0 History

<b>Document Identifier</b>	Date	Sections	Description
Draft versions:	02 Apr 2007	All	Initial version
OMA-TS-RME-V1_0			Minor restructuring in accordance with comments from tele con.
			Text changes in most sections. Clarified the events treatment
			Put the references in alphabetic order
	19 Apr 2007	1, 2	
	24 May 2007	10	Applied CR OMA-MAE-2007-0111R01
	19 Aug 2007	Multiples	Applies CRs
	20 Aug 2007	Multiples	Typo and editing.
	23rd August 2007	Multiples	CRs 186, 187 and 173 plus agreed change in document 183R03 and 171R01
	19 Sept 2007	Multiple	CR 194, CR 195, CR196
	02 Oct 2007	2.1, 11.3	CR 199R01
	17 Oct 2007	B, 11.1	CR 206R01, CR217R01, General editorial changes also made in multiple sections, Reviewed references and definitions.
	12 Nov 2007	12,	CR201R03
	16 Nov 2007	2,12	Added reference to UAPROF, Editorial corrections and formatting
	23 Nov 2007	9, 13, 6	CR232, MAE-2007-A200 Added section 6.3
	09 Apr 2008	All	Editorial updates:
			- 2008 template
			- Tables resized to fit
			- History box
			- Contents page fixed to show Table 1
	22 Sep 2008	All	Editorial fixes as per OMA-CONRR-RME-V1_0-20080626-D
Candidate version:	14 Oct 2008	All	Status changed to Candidate by TP:
OMA-TS-RME-V1_0			OMA-TP-2008-0376-INP_RME_V1_0_ERP_for_Candidate_Approval

# **Appendix B.** Static Conformance Requirements

(Normative)

The notation used in this appendix is specified in [SCRRULES].

## **B.1 SCR for RME Client**

Item	Function	Reference	Requirement
RME-SCENE_DESC- C-001-M			SVG:MCF
RME-SCENE_DESC- C-002-M	Support for extended scene description	Section 6.2	
RME-SCENE_ COMMAND-C-001-M	Support for scene mutation commands	Section 7.1	
RME-SCENE_ COMMAND-C-002-M	Support for scene state management commands	Section 7.2	
RME-SCENE_ COMMAND-C-003-M	Support for scene activation command	Section 7.3	
RME-SCENE_ COMMAND-C-004-M	Support for script command	Section 7.4	
RME-SCENE_ COMMAND-C-005-M	Support for setting stream time	Section 7.5	
RME-SCENE_ COMMAND-C-006-M	Support for command grouping	Section 7.6	
RME-SCRIPTING-C- 001-M	Support for script execution and integration	Section 8	ESMP-Language-C:MCF
RME-EVENT-C-001- M	Support for inherited events	Section 9.1	
RME-EVENT-C-002- M	Support for locally defined events	Section 9.2	
RME-EVENT-C-003- M	Support for event processing	Section 9.3	
RME-PROCESSING- C-001-M	Conform to RME processing rules	Section 10	
RME-DELIVERY-C- 001-M	Support RME data delivered in RME documents	Section 11.1	
RME-DELIVERY-C- 002-M	Support for RME in delivery contexts	Section 11	
RME-DELIVERY-C- 003-M	Support RME data delivered in 3gp files	Section 11.2 Section 11.5	
RME-DELIVERY-C- 004-O	Support Multi part MIME	Section 11.3	
RME-DELIVERY-C- 005-M	Support RME data delivered in RTP streams	Section 11.4	
RME-RESOURCES-C- 001-M	Support for resource usage	Section 13.1 Section 13.2 Section 13.3 Section 13.4	

# **Appendix C.** Font Usage for Content Authoring Guidelines (Informative)

It is strongly recommended that the original (unmodified) OpenType / TrueType fonts be used when support for custom fonts is required. In order to reduce the size of downloaded font data, fonts may be subsetted to include only those glyphs that represent characters in use by RME content. Please note that the process of conversion of OpenType / TrueType fonts to SVG font format is lossy. The conversion of fonts may also be prohibited by a font license. Please also note that the use of SVG fonts may increase the size of downloaded font data, may limit the ability to support some languages and will affect the text legibility (see [SVG], subclause 17.2).

# Appendix D. Definition of ECMA Script Bindings for uDOM Extensions

#### **Object TraitAccess**

#### getFloatTraitNS(namespaceURI, name)

This method returns a(n) Number. The **namespaceURI** parameter is of type **String**. The **name** parameter is of type **String**.

#### setFloatTraitNS(namespaceURI, name, value)

This method has no return value. The **namespaceURI** parameter is of type **String**. The **name** parameter is of type **String**. The **value** parameter is of type **Number**.

#### Object ScreenOrientationEvent

ScreenOrientationEvent has all the properties and methods of Event as well as the properties and methods defined below

The **ScreenOrientationEvent** has the following properties:

screenWidth This property is of type Number

screenHeight; This property is of type Number

screenAngle; This property is of type Number

softKeysLocation; This property is of type String

## Appendix E. UAProf Vocabulary Definitions

This section is informative.

#### E.1 RME Capable

#### E.2 RME Version

## **E.3** RME Delivery Contexts

```
<rdf:Description rdf:ID='RMEDeliveryContexts'>
    <rdfs:comment xml:lang='en'>
```

```
Description: List of RME Delivery contexts the device supports for transporting RME data streams. Property value is a list of supported contexts, where each item in the list is a context name.

Examples: "3GP", "http", "RTP"

</rdfs:comment>

<rdfs:label xml:lang='en'>RMEDeliveryContexts </rdfs:label>

<rdf:type rdf:resource='&ns-rdf;Property'/>

<rdfs:domain rdf:resource='#SoftwarePlatform'/>

<rdfs:range rdf:resource='&prf-dt;Literal'/>

<rdfs:range rdf:resource='&ns-rdf;Bag'/>

<pr
```

#### E.4 Screen Orientations

```
<rdf:Description rdf:ID='ScreenOrientations'>
   <rdfs:comment xml:lang='en'>
     Description:
                     Describes the list of supported screen
                      orientation capabilities. Note: there
                     is no notion of whether the display is
                     "upside-down" or not. "Portrait" is also
                     0 or 180 degrees. "Landscape" is also
                     90 or 270 degrees. "Angle" implies arbitrary
                     angular rotation.
      Examples: "portrait", "landscape", "angle"
  </rdfs:comment>
  <rdfs:label xml:lang='en'>ScreenOrientations</rdfs:label>
  <rdf:type rdf:resource='&ns-rdf;Property'/>
   <rdfs:domain rdf:resource='#SoftwarePlatform'/>
  <rdfs:range rdf:resource='&prf-dt;Literal'/>
  <rdfs:range rdf:resource='&ns-rdf;Bag'/>
   F:ResolutionRule rdf:datatype='&prf-dt;
       ResolutionRule'>Locked</prf:ResolutionRule>
</rdf:Description>
```

#### E.5 ScreenDefaultOrientation

#### E.6 CurrentScreenOrientation

```
<rdf:Description rdf:ID='CurrentScreenOrientation'>
   <rdfs:comment xml:lang='en'>
     Description:
                     Shows the current screen orientation. Portrait
                     is always long dimension vertical. Landscape is
                     always long dimension horizontal. An angular
                     reference assumes portrait is 0 or 180 degrees
                     and landscape is 90 or 270 degrees.
     Example: "portrait", "landscape", "270", "320"
   </rdfs:comment>
  <rdfs:label xml:lang='en'>CurrentScreenOrientation</rdfs:label>
  <rdf:type rdf:resource='&ns-rdf;Property'/>
  <rdfs:domain rdf:resource='#SoftwarePlatform'/>
  <rdfs:range rdf:resource='&prf-dt;Literal'/>
   cprf:ResolutionRule rdf:datatype='&prf-dt;
       ResolutionRule'>Override</prf:ResolutionRule>
</rdf:Description>
```

## E.7 CurrentRMEScreenSize